

HazMat Trucking Enforcer - Commercial Network Version Technical Requirements and Installation Instructions

HTEC is a PC based program that provides proper placarding, trailer marking, segregation, and emergency response guide information based on a limited number of inputs taken from a shipping manifest. Specialized Auditors covering shipping papers, package markings, package labeling, and motor cargo tanks provide additional review capabilities. Full-text Hazmat Regulations covering 49 CFR Parts 100-180, 200-399, and superceded Motor Cargo Tanks are included.

Minimum System Requirements:

- 64 MB memory
- 800x600 resolution
- 70 MB storage space

Server Installation Instructions

You must have administrator privileges to install the software. Once the software is installed, any users of the program will need to have write permissions to the directory where the program was installed.

- 1) Insert the HTEC CD into your computer's CD-ROM drive.
The CD should automatically start and run the setup program.

Note: If the installation does not begin automatically,
press WINDOWS Key+R
type "D:\Setup.exe" and press ENTER.
(If your CD-ROM drive is not D:, then substitute the correct drive letter.)

- 2) Follow the program installation instructions.

The default installation directory will be:
"c:\program files\Regscan\HazMat Trucking Enforcer - Commercial".

- 3) When the installation is complete, choose Finish. The HazMat Trucking Enforcer - Commercial is now installed.

- 4) Next step is the registration of the HTEC to the server.

Product Registration

Internet access is required to use the Automated registration process.

- 1) The first time HTEC is run on the server you installed it on it will need to register the program. This step will not be required of users the first time they run it using a desktop shortcut.
- 2) Run the program by double-clicking the "HTE - Commercial" desktop icon or by selecting "HTE Commercial" from the RegScan folder in your start menu.
- 3) The registration process will prompt for your company name and license key. This information was provided on your CD or in a letter / email.
- 4) After your unique Company name and license key are entered, continue to follow the registration procedure to complete the program registration.

Checking Preferences

- 1) Verify that the preferences are set in the manner your organization wants. To access preferences launch HTEC, go to the Edit Menu and select preference.
- 2) Make sure the saved loads path points to the directory that you want users to save loads to and that they have write access to that drive.

Setting Up User Computers

On each user computer you need to create a desktop shortcut to be used to launch the application.

- 1) Make sure that HTEC has been installed and registered on the server.
- 2) Create a desktop shortcut to the installed HTEC exe.
- 3) Each user will need write permissions to the in installed location on the server.

Issues on Saved Loads

The HTEC application allows saved loads to be saved in the directory specified by the saved loads path set on the preferences screen. This is a global setting. At the present time no capacity exists for saved loads to be saved in other than the single common directory.

It is recommended that when saving loads a prefix code be used if the trailer Ids are not unique. In this manner it is easier to find the load. Also the view option on the saved loads screen should be set to report view, rather than preview view.